



## Release Notes - Build 2.0.26.2305 (September 13, 2024)

---

Welcome to Titan DMZ Server, the latest iteration of our secure reverse proxy server.

### Installation Process

---

Please review the [Minimum System Requirements](#) located at the bottom of this document to ensure compatibility with your environment.

If installing Titan DMZ Server over an existing DmzEdge 2019 installation, please review the [Updating a DmzEdge Installation](#) section below

To install the software, double-click on the installation program and follow the instructions in the installer. There is no need to Run-As-Administrator. The installer will check to ensure that adequate permissions are available to install the software.

If you encounter any issues while running this software, please report them to our technical team through our online helpdesk. The helpdesk is located at <https://helpdesk.southernverttech.com/>

### Features and Enhancements

---

- There is a completely new web-based administration console
- Titan DMZ has been re-architected from the ground up and is now cross-platform with support for 64-bit versions of both Windows and Linux

## Build 2.0.26.2305 (September 13, 2024)

---

#### *Features and Enhancements:*

- Updated components and security engines to latest builds

#### *Bug Fixes:*

- [NX-11495] Security Changes: Changed the web UI to encrypt sensitive information sent to the server and to not return any sensitive information in web responses.



## Minimum System Requirements

---

- The Web-based Admin Console and the WebUI require the latest versions of Microsoft Edge, Google Chrome, or Mozilla Firefox. **Microsoft Internet Explorer (IE) is not supported**
- 64-Bit Windows 10 Professional or later (32-bit is not supported)
- 64-Bit Windows Server 2016 or later (32-bit is not supported)
- A 2Ghz Pentium class processor is required, multi-core is recommended
- 8GB of RAM is required, 16GB is recommended for production systems
- TLS 1.3 support is only available under Windows Server 2019 and Windows Server 2022



## Updating a 2019 Version Installation

---

When updating a DMZedge Server 2019 installation, the Titan DMZ Server installer will create a full backup of the DMZedge Server 2019 configuration.

On Windows, backups will be stored under the folder

`\ProgramData\South River Technologies\DmzEdge\Backups\`

Once the installer has installed DMZedge Server, it will optionally import the configuration information from the Legacy DMZedge Server installation.

NOTE: Although no modifications are made to Legacy installation, the DMZedge Server installation program will stop the DMZedge Server 2019 Windows Service and set the auto-start mode to Disabled. This is done to prevent conflicts between the DMZedge Server 2019 configuration and Titan DMZ Server. The installer will enable the Titan DMZ Server service instead.

To return to a DMZedge Server 2019 environment, simply Uninstall the Titan DMZ Server product and then Enable the DMZedge Server 2019 Windows Service in the Windows Control Panel.

For more information related to updating a DMZedge Server 2019 system to Titan DMZ Server, please visit our helpdesk at <https://helpdesk.southernrivertech.com/>